

Vibe PC Installation Instructions (R_5.0)

Dear Customers, in this document we will give instructions on how to install the Vibe PC software.

You'll need a computer with an active internet connection to download the software.

Minimum requirements:

- Windows 10 at least.
- 8GB of disk space (preferably SSD).
- 8GB of RAM.
- OpenGL version 4.3.
- Recommended – external graphic card.
- Recommended – strong CPU.


Limitations:

- A Stand-alone PC instance will have free 64 universes of VC, 1 Artnet and 1 sACN.
- A Stand-alone PC instance will have random 10 second blackouts.
- Expansion options:
 - o Any ePort will open additional Artnet and sACN universes (ePort2 will open 2, ePort8 will open 8 etc.)
 - o A PC Wing (also Vector PC Wings) will open 16 universes.
 - o The only way to remove the random blackouts, at the moment, is by connecting to a PC Wing.

ATTENTION!!! The PC software installation is needed only the first time. The future releases can be installed directly from the software's Offline Tool, with the Software Updates function.

Installation Process:


1. On a computer with internet connection download the zip file.
2. Extract the Zip file and you will get the Self-Extract .exe file.
3. **Run as Administrator** the **Vibe PC R_5.0.exe** file.
4. The self-extract operation will start. It may take a few seconds.
5. Once finished, if not installed already on your computer, you will be asked to install some pre-requisites on this window:




Click Install.

(If you don't get this window, it means your PC already have what's needed).

Let the installation finish. If prompted while the process is active, restart the PC and the installation process will continue automatically after the restart.



- The next stage is to install SQL Server 2019 (Vibe uses it as its database).




Click Yes.

(If you don't get this window, it means your PC already have what's needed).


Let the installation finish, it can take a few minutes.

- Once the SQL Server installation is finished, the installation should continue automatically from this screen:




Click Next.


8. On the next screen, accept the terms and conditions and click Next.




9. On the next screen choose the destination folder and whether you want shortcuts to the Vibe and click Next.




10. On the next screen you will get a summary of the installation settings. Make sure everything is ok and once ready click Install.




11. The installer will now copy files and config what's needed for the Vibe software, including running some scripts.





12. Once finished, you will get the completion screen. You can decide if to run Vibe and/or show the installation log file. Choose the desired options and click Finish.



Your Vibe PC is now ready!



We recommend you have a look on the manual at - <https://vibemanual.compulite.com/>

On any question you can contact – support@compulite.com

For fixture requests you can contact – fixturesupport@compulite.com